Volume Graphics Reconstruction Geometry and Coordinate System Conventions

The axes referred to in this documentation are as follows: the z-axis is the "vertical" axis, i.e., the upwards direction of the (optimum) rotation axis. The x-axis is perpendicular to the detector plane, going from x-ray source to detector. The y-axis is, therefore, the "horizontal" detector axis.

Fig. 1:

Geometric setup (top view)





Fig. 3:

Geometric setup, detector (frontal)



ړ ا

Legend:

 $R_{\scriptscriptstyle E}$ distance focus — isocenter

 $R_{\rm D}$ distance isocenter — detector

C center of the misaligned detector

C' isocenter projected on the detector plane

 d_{upo} horizontal detector offset

V volume to be reconstructed

 $r_{\rm cc}$ center ray

D detector

F focus of the source



Geometric setup with reconstruction volume cube at zero angle





Fig. 4:

Geometric setup, detector (frontal)





d_{vpo} vertical detector offset

 W_{pot} detector width (corresponding number of pixels x pixel width)

 h_{Det} detector height (corresponding number of pixels x pixel height)

volume edge length (result physical size)

 τ rotation axis tilt angle



Speyerer Straße 4-6 | 69115 Heidelberg, Germany Phone: +49 6221 73920-60 | Fax: +49 6221 73920-88 sales@volumegraphics.com | www.volumegraphics.com